















↻ The Rotor






The Rotor allows the user to choose from a list of navigation options, including Containers, Headings, Landmarks, Same item, Vertical Navigation, Static text, Links, Tables, Lists, Buttons, Form Controls, Text fields, Search Fields, and Images.

Twist two fingers in a circle to choose a setting on the rotor. Left and right swipes go to the next element on the page, up and down swipes go the next element of the type selected in the rotor. The settings for what appears in the rotor are highly customizable. If an option you want is not appearing, navigate to Settings > General > Accessibility > Voiceover > Rotor to enable it.

Getting Started

<p>Turn VO on/off (When setting is enabled)</p>  <p>Triple-press home button or side button (iPhone X +)</p>	<p>Pause/restart reading</p>  <p>Two-finger tap</p>	<p>Start reading continuously from this point on</p>  <p>Two-finger swipe down</p>	<p>Read entire page</p>  <p>Two-finger swipe up</p>	<p>Read next item</p>  <p>Swipe right</p>
<p>Activate link or button</p>  <p>Double-tap</p>	<p>Go back, close popup, cancel last</p>  <p>Two-finger scrub</p>	<p>Item Chooser:</p>  <p>Two-finger triple-tap</p>	<p>Navigate table cells</p>  <p>Swipe up, down, left or right</p>	<p>Go to next list item</p>  <p>Swipe right</p>
<p>Go to first item on page</p>  <p>4-finger tap upper half of screen</p>	<p>Scroll (vertically or horizontally)</p>  <p>3-finger swipe up, down, left, or right</p>	<p>Go back one link, list, table, landmark, heading, etc.</p>  <p>Swipe up</p>	<p>Help with current element</p>  <p>Rotor (Hints), swipe up/down to enable hints</p>	

Reading Text

<p>Say prior line, word, character</p>  <p>Rotor, swipe up</p>	<p>Say next line, word, character</p>  <p>Rotor, swipe down</p>	<p>Say from current</p>  <p>Two-finger swipe down</p>	<p>Say character phonetically</p>  <p>Settings > VO > Phonetic feedback</p>	<p>Toggle speech on/off</p>  <p>Three-finger double-tap</p>
---	--	--	--	--

Forms

Next form or button




Rotor, swipe down

Select and deselect checkboxes, radio buttons, combo box options



Double-tap

Next checkbox, combo box, radio button



Rotor (Same item or form controls), swipe down

Open combo box



Double-tap

Hide combo box options:



Drag finger through list


Text Editing

Select/deselect text



Pinch out/in

Copy the last spoken text to the clipboard



Three-finger quadruple-tap

Change case



Three-finger swipe up/down*

Insert space



Two-finger swipe right*


Backspace



Two-finger swipe left*

Table

Go to next table



Rotor, swipe down

Cell to right




Swipe right

Cell to left



Swipe left

Cell below



Swipe down


Cell above



Swipe up


Other Commands

Gesture help



4-finger double-tap

Split tap quick-activation



Select and hold with one finger, tap with another

Double-press button




Triple-tap

Speak words or characters typed



Settings > General > VoiceOver > Typing Feedback

Next/previous app




4-finger swipe right/left

Drag mode



Tap twice and hold

Toggle screen curtain on/off (VO works but screen is off)



Three-finger triple-tap

*This gesture only works in handwriting mode, not in typing mode.

Full list of commands: <http://tinyurl.com/commands-voiceover-ios>